


## excelliSCAN Scan Heads – Functional Principle of SCANahead Servo Control and Operation by RTC<sup>®</sup> 6 Boards



**SCANLAB AG**

Siemensstr. 2a  
82178 Puchheim  
Germany

Tel. +49 (89) 800 746-0

Fax: +49 (89) 800 746-199

[info@scanlab.de](mailto:info@scanlab.de)

[www.scanlab.de](http://www.scanlab.de)

© SCANLAB AG 2016

(Doc. Rev. 1.0.0 e - February 29, 2016)

SCANLAB reserves the right to change the information in this document without notice.

No part of this manual may be processed, reproduced or distributed in any form (photocopy, print, microfilm or by any other means), electronic or mechanical, for any purpose without the written permission of SCANLAB.

RTC® is a registered trademark of SCANLAB AG.

Other mentioned trademarks are hereby acknowledged as properties of their respective owners.



## Contents

<b>1 Overview</b>	<b>4</b>
1.1 Introduction	4
1.2 About This Manual and Other Documents	4
<b>2 excelliSCAN Scan Heads with SCANAhead Servo Control</b>	<b>5</b>
2.1 Introduction	5
2.2 Comparing excelliSCAN Scan Heads to Scan Heads with Conventional Servo Control (for example, intelliSCAN®)	6
2.2.1 What is Unchanged for excelliSCAN Scan Heads?	6
2.2.2 Comparing Scan Heads with and without SCANAhead Technology	7
2.2.3 Returned Data Signal Differences: PosAck Status Signal Behavior after Limit Exceedance	10
2.2.4 Returned Data Signal Differences: New Status Value HEAD_BUSY	11
2.2.5 Returned Data Signal Differences: Change of Meaning for 0x0502 Signal	11
2.2.6 New Returned Data Signal: New Type for SetControlDefinitionMode	11
2.2.7 Timing Diagram of excelliSCAN 14 Scan Head with SCANAhead Technology	12
2.3 excelliSCAN-Specific Changes of Returned Data with the control_command Command	14
control_command	14
<b>3 RTC®6 SCANAhead Functions</b>	<b>16</b>
3.1 Introduction	16
3.2 Quick Migration Guide	18
3.2.1 Example Source Code	19
3.2.2 Modifying Existing User Programs for excelliSCAN Scan Heads – Basic Steps	20
3.2.3 Modifying Existing User Programs for excelliSCAN Scan Heads – Taking Restrictions into Account	20
Non-Usable Functionalities of the RTC®6 Board and RTC®6 DLL	20
Non-Usable iDRIVE® Functionalities	21
3.3 Modifying Existing User Programs – Further Steps, Background Info on SCANAhead and excelliSCAN Functions	22
Notes on Using Commands for Scanner Delays and Laser Delays	22
Notes on Arc Commands	22
Notes on Polygon Delays	23
Notes on Sky Writing	23
Notes on Functions for Automatic Laser Control	24
Notes on Controlling Peripherals	24
Notes on Unique Characteristics of Returned Data Signals	24
Notes on PosAck Status Signal Behavior	24
3.4 RTC®6 Commands - Exclusively for SCANAhead Systems	25
activate_scanahead_autodelays	25
activate_scanahead_autodelays_list	26
get_scanahead_params	26
set_scanahead_laser_delay_shift	28
set_scanahead_laser_delay_shift_list	28
set_scanahead_line_params	29
set_scanahead_line_params_list	29
set_scanahead_params	30



## 1 Overview

### 1.1 Introduction

Because SCANLAB excelliSCAN scan heads use SCANahead servo control, they exhibit different dynamics than scan heads with conventional control.

In particular, you need to consider timing differences when synchronously operating your scan head, laser and peripheral equipment.

Here, the RTC®6 board command set provides special SCANahead commands that considerably simplify adapting of existing RTC applications (for conventional scan heads) into programs for excelliSCAN scan heads with SCANahead control. Basically, just add two lines of code to your existing RTC®6 program:

```
set_scanahead_params( 1, 1, 1, 0, 0, 0 );  
activate_scanahead_autodelays( 1 );
```

All details about these and other commands are described in this manual.

#### Notes

- All references to the RTC®5 manual refer to Doc. Rev. 1.10 e.

### 1.2 About This Manual and Other Documents

This manual describes user-relevant differences between excelliSCAN scan heads with SCANahead servo control and scan heads with conventional control. And it describes all special RTC®6 commands reserved exclusively for operating SCANahead-based excelliSCAN scan heads.

Thus, this document expands upon the RTC®6 and RTC®5 manuals. To program complete RTC®6 applications for SCANahead-based excelliSCAN scan heads, you have to observe all three manuals. Also observe the notes in your scan head manual.


## 2 excelliSCAN Scan Heads with SCANahead Servo Control

### 2.1 Introduction

excelliSCAN scan heads are equipped with SCANahead servo control. This innovative control concept<sup>(1)</sup>:

- Produces no tracking error and
- Exploits the maximum acceleration capability of the galvanometer scanners.

Figure 1 shows how SCANahead servo control is structured.



Structure of SCANahead servo control (timing depictions are not true-to-scale)

The RTC<sup>®</sup>6 board puts out RTC control values. The preprocessing unit analyzes associated theoretical accelerations. These are then limited to match the scan system's actual acceleration capabilities.

The result is a precalculated set trajectory of acceleration-limited control values.

The required time for this is depicted as ReferencePreprocessing in figure 1 and figure 4.

The galvanometer scanner control successfully traverses the precalculated set trajectory (actual trajectory in figure 1) – but only with a temporal offset (the control preview time ControlPreview, see figure 1 and figure 4). This enables full usage of scan system dynamics.

The entire temporal offset between RTC control values and galvanometer scanner motions (that is, ReferencePreprocessing plus control precalculation time ControlPreview) is called PreviewTime. The term PreviewTime highlights the excelliSCAN scan head's need to know the RTC control values in advance by this amount of time to ensure punctual execution.

For synchronous laser control, the laser control signals likewise need to take PreviewTime into account. This also applies for any other control signals intended to be transmitted synchronously with scanner motion.

The RTC<sup>®</sup>6 can ensure synchronous operation of galvanometer scanner motions, laser control, and other peripherals.

The precalculated set trajectories with limited, constant set accelerations cause acceleration time to vary in accordance with speed changes. This means scanner delays and laser delays needed for taking acceleration time into account are also dependent on speed.

The RTC<sup>®</sup>6 board can automatically calculate the required delays. Therefore, SCANLAB recommends the RTC<sup>®</sup>6 for operating excelliSCAN scan heads with SCANahead technology, see chapter 3.1 "Introduction", page 16.

(1) Thus, excelliSCAN scan heads cannot be operated like conventional scan heads.

## 2.2 Comparing excelliSCAN Scan Heads to Scan Heads with Conventional Servo Control (for example, intelliSCAN®)

### 2.2.1 What is Unchanged for excelliSCAN Scan Heads?


What is described in the RTC®5 manual [chapter 7.2 "Delay Settings for Synchronizing Scan Head and Laser Control"](#), [page 108](#) also applies when controlling an excelliSCAN scan head by an RTC®6 board:

- The galvanometer scanner motions are temporally offset from the RTC control values by the `PreviewTime` (not: tracking error!). For details, see the table in [chapter 2.2.2 "Comparing Scan Heads with and without SCANahead Technology"](#), [page 7](#).
- The temporal stream of actual values (=actual trajectory) is smoothed in comparison to the stream of RTC control values<sup>(1)</sup>, due to the limited acceleration potential of galvanometer scanners.
- To compensate the temporal offset between RTC control values and actual trajectories when synchronizing galvanometer scanner motions and laser signals, the RTC®6 allows setting of scanner and laser delays.  
The meaning of delays for the excelliSCAN is the same as for scan systems without SCANahead technology (and identical for both the RTC®6 and RTC®5 boards). The same applies for the commands `set_scanner_delays` and `set_laser_delays` to set the delays.
- The preferable alternative is to let the RTC®6 board automatically calculate and set scanner delays and laser delays, see [chapter 3.1 "Introduction"](#), [page 16](#).

(1) Thus any curves within the control value trajectory get reduced.

## 2.2.2 Comparing Scan Heads with and without SCANahead Technology

SCANahead technology makes excelliSCAN scan heads behave differently in some respects than scan heads without SCANahead technology. These differences are contrasted in [figure 2](#) and the following table.



Comparison: Conventional galvanometer scanner servo control and SCANahead servocontrol control

Scan Head without SCANahead Technology	Scan Head with SCANahead Technology, for example, excelliSCAN
<ul style="list-style-type: none"> <li>Scan heads without SCANahead technology exhibit a characteristic temporal offset called tracking error <math>t_s</math>, see <a href="#">figure 2</a>. The tracking error <math>t_s</math> results from the implemented servo control structure. The tracking error duration <math>t_s</math> is a metric for the dynamics of a scan head. The tracking error <math>t_s</math> is (at "normal" speeds) practically independent of scan speed. It is also affected by the selected tuning.</li> </ul>	<ul style="list-style-type: none"> <li>For scan heads with SCANahead technology, the temporal offset is not tracking error <math>t_s</math>. Instead it is the fixed, pre-defined precalculation time <math>\text{PreviewTime } t_p</math>, see <a href="#">figure 2</a>. The precalculation time <math>\text{PreviewTime } t_p</math> is qualitatively different from tracking error <math>t_s</math>. And it is not a metric for scan head dynamics. Instead, a physically traversable trajectory gets precalculated within the <math>\text{PreviewTime } t_p</math>.</li> </ul>

Scan Head without SCANahead Technology (Continued)	Scan Head with SCANahead Technology, for example, excelliSCAN (Continued)
<ul style="list-style-type: none"> <li>Tracking error <math>t_s</math> can introduce undesirable artifacts during marking, for example, “necking” in circles and arcs. You can partially compensate such artifacts by specifying over-dimensioned set radii.</li> </ul>	<ul style="list-style-type: none"> <li>Vectors can be traversed even at very high speeds. Necking artifacts during circle/arc marking only start to occur at accelerations exceeding <math>A_{max}^{(a)}</math>. Therefore, these necking artifacts can <i>not</i> be compensated by specifying larger set radii!</li> </ul>
<ul style="list-style-type: none"> <li>For tracking error <math>t_s</math>, a tolerance (maximum value) is specified (tested by SCANLAB). But the exact value can be serial-number-dependent (minor variation within the tolerances are possible). The exact value cannot be queried, and must instead be experimentally determined.</li> </ul>	<ul style="list-style-type: none"> <li>The PreviewTime <math>t_p</math> is a serial-number-dependent value. It is permanently stored in the firmware and can be queried from the scan head.</li> </ul>
<ul style="list-style-type: none"> <li>The trajectory of RTC control values gets smoothed by servo control. The result of smoothing is not precisely known in advance. And it is dependent on the selected tuning. In negative acceleration phases, significant undesirable overshoot may occur.</li> </ul>	<ul style="list-style-type: none"> <li>From the trajectory of RTC control values, a traversable acceleration-limited set value trajectory gets calculated and transmitted to the servo control, see <a href="#">figure 1</a>. Deviation of the final actual value trajectory from the RTC control value trajectory is therefore known in advance (because it was precalculated).</li> </ul>
<ul style="list-style-type: none"> <li><i>The duration of acceleration phases is practically speed-independent.</i> Thus the same amount of time is always required to reach the desired target speed. This means that, particularly at low speeds, the acceleration potential is not fully exploited and the process times of applications are therefore not optimal.</li> </ul>	<ul style="list-style-type: none"> <li>SCANahead control ensures constant acceleration (at the maximum capabilities of the scan head) in acceleration phases. <i>The duration of acceleration phases is thus minimized, although speed-dependent.</i> Resultingly, scanner delays and laser delays need adjusting in accordance with marking speed.</li> </ul>



Scan Head without SCANahead Technology (Continued)	Scan Head with SCANahead Technology, for example, excelliSCAN (Continued)
<ul style="list-style-type: none"> <li>You can set scanner delays and laser delays: These do <i>not</i> need adjusting for changes in speed. There are rules of thumb for sizing the delays, but truly optimal delays always require empirical determination for each case of application. Furthermore, delay values need determining for each tuning.</li> </ul>	<ul style="list-style-type: none"> <li>You can set scanner delays and laser delays: They must be set <i>differently in accordance with speed</i>. Thanks to constant acceleration and precalculated set positions, the relationship between speed and optimum delays is likewise mathematically known in advance. The RTC<sup>®</sup>6 board can automatically determine the optimal speed-dependent scanner delays and laser delays. It then also sets them dynamically in real time during list execution. For this, the user activates RTC<sup>®</sup>6 autodelay functionality by <b>set_scanahead_params</b> and <b>activate_scanahead_autodelays</b><sup>(1)</sup> as described in chapter 3.1 "Introduction", page 16 with figure 5 and figure 6. If the user does <i>not</i> want to use RTC<sup>®</sup>6 autodelay functionality (<b>set_scanahead_params</b> and <b>activate_scanahead_autodelays</b><sup>(0)</sup>), then: <ul style="list-style-type: none"> <li>Speed-dependent delays "must" be determined and</li> <li>appropriately set before each change of speed</li> </ul> </li> </ul>

(a) Therefore, at very high speeds or for very small radii. See also empirical formula in "Notes on Arc Commands", page 22.


## 2.2.3 Returned Data Signal Differences: PosAck Status Signal Behavior after Limit Exceedance

Both scan heads with iDRIVE® technology and excelliSCAN scan heads return the PosAck status signal at 10  $\mu$ s intervals. But the following differences apply after exceedance of the threshold value, see figure 3:

- For non-excelliSCAN scan heads, the PosAck bit gets automatically reset to 1 as soon as the position error is smaller than the limit value.
- For excelliSCAN scan heads, the PosAck bit is not automatically reset to 1 as soon as the position error is smaller than the limit value. That is, the PosAck bit remains at 0.

*This lets you determine after the event whether a limit exceedance has been occurred.*

To reset the PosAck bit to 1, you must execute `control_command (Data = 0x403A)`.



PosAck signal for non-excelliSCAN and excelliSCAN scan heads

## 2.2.4 Returned Data Signal Differences: New Status Value HEAD\_BUSY

A new addition to the RTC<sup>®</sup>6 board in comparison with the RTC<sup>®</sup>5 is the returnable status value HEAD\_BUSY (bit #23).

This status value only gets returned by excelliSCAN scan heads. It can be queried by the **get\_status** control command, see also the RTC<sup>®</sup>5 manual chapter 6.4.3 “List Execution Status”, page 77.

A prerequisite for this is that **set\_scanahead\_params** with valid parameters has been called. That is, the RTC<sup>®</sup>6 board is configured to operate excelliSCAN scan heads.

The HEAD\_BUSY status value is returned when:

- A list is being processed
- A list has been finished, but scan head output is still in progress (temporal offset = PreviewTime)
- The marking’s final still-in-progress Laser-OffDelay has not yet expired, that is, so long as the laser is still on

This allows waiting until the actual end of marking before an equipment controller closes a shutter or power is cut to the scan head, etc.

In contrast, if the laser was manually switched on (**laser\_signal\_on**) after the list ended but before expiration of PreviewTime, then its LASEROFF is not be waited for.


## 2.2.5 Returned Data Signal Differences: Change of Meaning for 0x0502 Signal

The value 0x0502 returned by excelliSCAN scan heads has a different meaning than for non-excelliSCAN scan heads, see chapter 2.3 “excelliSCAN-Specific Changes of Returned Data with the control\_command Command” and chapter 2.2.7 “Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology”, page 12.

## 2.2.6 New Returned Data Signal: New Type for SetControlDefinitionMode

In response to the **SetControlDefinitionMode** command, excelliSCAN scan heads return the value 4 (SCANahead trajectory control), see page 15 in chapter 2.3 “excelliSCAN-Specific Changes of Returned Data with the control\_command Command”.

## 2.2.7 Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology



Timing diagram of excelliSCAN 14 scan head

Note: In the timing diagram (figure 4), specified absolute time values are for the excelliSCAN 14.

For excelliSCAN scan heads, the signal 0x0502 is the already acceleration-limited precalculated set position (angular position). This value can be queried with control\_command (Data = 0x0502).

This 0x0502 signal is delayed with respect to RTC control values by ReferencePreprocessing (excelliSCAN 14: 100×10 μs clock cycles, that is, 1.0 ms).

Each precalculated set position value 0x0502 is reached after the control preview time ControlPreview (excelliSCAN 14: exactly 20×10 μs clock cycles, that is, 0.2 ms).

The trajectory of actual positions 0x0501 therefore lags the trajectory of precalculated set positions 0x0502 by 0.2 ms and lags the RTC control values by 1.2 ms (PreviewTime).

For excelliSCAN, the signal 0x0503 (position error) is the difference between the precalculated set position 0x0502 (at 1.0 ms after the RTC control value) and the actual position 0x0501 at 1.2 ms after the RTC control value (and 0.2 ms after the precalculated set value). This value can be queried by control\_command (Data = 0x0503).



The galvanometer scanner position error – even during acceleration phases – is very small (that is, practically a straight line). You can therefore select a very small PosAck threshold value (in comparison to conventional scan heads) without the limit value being exceeded and the PosAck bit getting set.

As the example timing diagram shows, the position error is calculated as follows:  $0x0503$  @ clock cycle<sub>n</sub> =

$0x0502$  @ clock cycle<sub>n-20</sub> –  $0x0501$  @ clock cycle<sub>n</sub>.

Users who intend to calculate the control error themselves from log files have to observe this relationship.

With logging software, the signal  $0x0503$  is therefore depicted as x-axis-parallel line (that is, nearly horizontal line at 0).

## 2.3 excelliSCAN-Specific Changes of Returned Data with the control\_command Command

Ctrl Command	control_command		
Function	Sends a control command to an excelliSCAN scan head (firmware versions >5050).		
Call	control_command( Head, Axis, Data )		
Parameters	Head	See RTC5 manual.	
	Axis	See RTC5 manual.	
	Data	See RTC5 manual.	
		<b>Code<sub>H</sub></b>	<b>Command and parameter values (Code<sub>L</sub>)</b>
		05 <sub>H</sub>	<b>SetMode:</b> See RTC5 manual. As described there: – Each Code <sub>L</sub> parameter value corresponds to a specific data type. – The standard setting is Code <sub>L</sub> = 00 <sub>H</sub> (XY2-100 status word).  excelliSCAN scan systems have an SL2-100 interface. They therefore return a signed 20-bit status value.
			<b>Code<sub>L</sub></b> <b>Data type returned by scan system</b>
		01 <sub>H</sub>	For NON-excelliSCAN and excelliSCAN scan heads, the following applies: Actual position (angular position of galvanometer scanners). Bits [–2 <sup>19</sup> ... 2 <sup>19</sup> –1].  See chapter 2.2.7 “Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology”, page 12 and figure 4.
		02 <sub>H</sub>	For NON-excelliSCAN scan heads, the following applies: Set position (galvanometer scanners’ angular position). Bits [–2 <sup>19</sup> ... 2 <sup>19</sup> –1].  For excelliSCAN scan heads, the following applies: Precalculated set position (angular position of galvanometer scanners). Bits [–2 <sup>19</sup> ... 2 <sup>19</sup> –1].  See chapter 2.2.7 “Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology”, page 12 and figure 4.
		03 <sub>H</sub>	For NON-excelliSCAN and excelliSCAN scan heads, the following applies: Position error (= set position – actual position). Bits [–2 <sup>19</sup> ... 2 <sup>19</sup> –1].  See chapter 2.2.7 “Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology”, page 12 and figure 4.

Ctrl Command	control_command		
	0A <sub>H</sub>	<b>UpdatePermanentMemory.</b> This command has no effect on excelliSCAN scan heads.	
	0E <sub>H</sub>	<b>SetControlDefinitionMode</b> As described in the RTC <sup>®</sup> 5 manual. Additionally, the value 4 is the tuning type for excelliSCANs.	
		<b>Code<sub>L</sub></b>	<b>Value returned by scan head</b>
		00 <sub>H</sub> ... 03 <sub>H</sub>	Bits #4...7 Tuning type: (...) = 4: SCANahead servo control.
	11 <sub>H</sub>	<b>SelectControlDefinition.</b> This command has no effect on excelliSCAN scan heads. Only one tuning is available for excelliSCAN scan heads.	
	12 <sub>H</sub>	<b>SetPositionScale.</b> This command has no effect on excelliSCAN scan heads. With excelliSCAN scan heads, the effective calibration cannot be changed.	
	40 <sub>H</sub>	<b>ResetPOSACK.</b> For excelliSCAN scan heads, this command lets you reset the PosAcknowledge warning. The only allowed parameter value for this command is Code <sub>L</sub> = 3A <sub>H</sub> . See also RTC <sup>®</sup> 5 manual <a href="#">chapter 8.1.6 "Configuring the PosAcknowledge Threshold Value"</a> , <a href="#">page 178</a> , <a href="#">page 279</a> , <a href="#">page 282</a> as well as in this document <a href="#">chapter 2.2.3 "Returned Data Signal Differences: PosAck Status Signal Behavior after Limit Exceedance"</a> , <a href="#">page 10</a> . Note: Because the <b>UpdatePermanentMemory</b> command has no effect on excelliSCAN scan heads, the PosAcknowledge threshold value cannot be saved for subsequent new starts or resets.	
Notes	General notes: <ul style="list-style-type: none"><li>–</li></ul>		
Version info	Status: Version DLL 601.		
References	<b>get_value, get_values, get_head_status, get_value, set_trigger, set_trigger4, get_waveform, get_last_error</b>		

## 3 RTC®6 SCANahead Functions

### 3.1 Introduction

As previously explained, the excelliSCAN scan head internally calculates a set trajectory with limited, constant accelerations, whereby the acceleration time depends on speed changes. Resultingly, the scanner and laser delays needed for taking acceleration time into account depend on speed.

The RTC®6 board can automatically calculate the required delays. For this and other reasons, SCANLAB recommends the RTC®6 for operating excelliSCAN scan heads and other SCANahead-based scan heads.

Two commands “activate” RTC®6 SCANahead functionality for suitable control of excelliSCAN scan heads:

#### (1) **set\_scanahead\_params** (Mode =1)

The RTC®6 board queries relevant information from the scan head, processes it if needed (coordinate transformations etc.) and holds it for further usage. Additionally, the board’s laser control section gets prepared for taking PreviewTime into account. This affects LASER\_DIGITAL\_OUT1/2 etc., see “Notes on Controlling Peripherals” on page 24.

#### (2) **activate\_scanahead\_autodelays** <sup>(1)</sup>

The RTC®6 is instructed:

- To use the results of (1).
- To ignore delays set in source code by **set\_scanner\_delays** and **set\_laser\_delays**.
- To automatically calculate (for high contour fidelity) optimal speed-dependent scanner delays and laser delays<sup>(1)</sup>.
- To also set these dynamically in real time during list execution.
- To likewise automatically calculate all required parameters when sky writing is used (for example, run-in and run-out motions), see also “Notes on Sky Writing”, Seite 23.

Thus, users can effortlessly and immediately create markings with high contour fidelity <sup>(2)</sup> (without the need to determine and optimize delays).


Of course, users are also free to tailor marking results using additional suitable RTC®6 commands:

- *Scanner delays* are influenced by the **CornerScale** and **EndScale** parameters of the two commands **set\_scanahead\_line\_params** and **set\_scanahead\_line\_params\_list**. The effects of these parameters are shown in figure 5. You can choose between optimal contour fidelity and optimal process speed at the cost of contour fidelity (*process optimization*).
- *Laser delays* are influenced by the **AccScale** parameter of the two commands **set\_scanahead\_line\_params** and **set\_scanahead\_line\_params\_list**. The effect of this parameter is shown in figure 6. Here, you can influence energy deposition at line ends by partially or wholly show/hide acceleration phases.
- Also available for *fine-tuning* laser delays are the RTC®6 commands **set\_scanahead\_laser\_delay\_shift** and **set\_scanahead\_laser\_delay\_shift\_list**. They let you set a temporal offset for the laser switching time points, for example, to compensate signal propagation times.


(1) For all commands that require delays, that is, jump, mark, arc commands.

(2) Provided that the specified marking speed makes sense. However, the jump speed is automatically reduced to suitable values.





Command `set_scanahead_line_params(_list)`, parameter `CornerScale` and parameter `EndScale` (influence scanner delays)



Command `set_scanahead_line_params(_list)`, parameter `AccScale` (influences laser delays)



## 3.2 Quick Migration Guide

This chapter gives advanced users the following practical information for quickly transitioning to an excelliSCAN scan head with an RTC<sup>®</sup>6 board:

- Example source code for a user application, see [chapter 3.2.1 "Example Source Code", page 19](#)
- Tips on adapting existing RTC user applications for the excelliSCAN, see [chapter 3.2.2 "Modifying Existing User Programs for excelliSCAN Scan Heads – Basic Steps", page 20](#)
- A summary of what is no longer applicable compared to the RTC<sup>®</sup>5 or scan heads without SCANahead technology, see [chapter 3.2.3 "Modifying Existing User Programs for excelliSCAN Scan Heads – Taking Restrictions into Account", page 21](#)

Further details are provided starting with [chapter 3.3 "Modifying Existing User Programs – Further Steps, Background Info on SCANahead and excelliSCAN Functions", page 22](#).



### 3.2.1 Example Source Code

The following example code snippets illustrate basic elements of an RTC®6 user application to initialize the RTC6DLL.DLL and RTC®6 board (that is, the example is not compilable).

Because this example uses implicit linking, the files RTC6impl.h and RTC6DLL.LIB are required. Additionally, the program needs to be able to call RTC6DLL.DLL. If the operating system can not find RTC6DLL.DLL during program start, then it responds with an error message and terminates the program.

```
// SAMPLE SOURCE CODE SNIPPETS: TO MARK A SQUARE.
//
// RTC®6 header file for implicit linking to RTC6DLL.DLL.
// also link to Visual C++ import library RTC6DLL.LIB, to compile an executable
#include "RTC6impl.h"

// scanahead line params
CornerScale = 100;    // polyline: 100%: max precision, 0% min execution time
EndScale = 100;      // mark, jump: 100%: max precision, 0% min execution time
AccScale = 100;      // 100%: laser is on during acceleration and deceleration
// 0%: laser is off during acceleration and deceleration

// enable/disable variable polygon delay or sky writing
VariablePolygonDelay = 0;
SkyWriting = 0;
int main()
{

// initialize
init_rtc6_dll();
if( 0 != load_program_file( NULL ) ) { return -1; }           // load RTC firmware
if( 0 != load_correction_file( NULL, 1, 2 ) ) { return -2; }
set_mark_speed_ctrl( 25000 );
set_jump_speed_ctrl( 50000 );

// laser control
set_laser_control( 0 );                                     // high active laser signals
set_laser_mode( 1 );                                       // mode 1 supports YAG
set_firstpulse_killer( 640 );
set_laserpulses_ctrl( 320, 128 );

// scanahead: calculate delays automatically. excelliSCAN scan head must be connected and powered.
set_scanahead_params( 1, 1, 1, 0, 0, 0 );                  // place anywhere after load_correction_file
activate_scanahead_autodelays( 1 );
set_scanahead_line_params( CornerScale, EndScale, AccScale );
set_scanahead_laser_shifts( 50, 50 );                      // fine tuning LaserON and LaserOFF

// sky writing and variable polygon delay
set_delay_mode( VariablePolygonDelay, 0, 2^30, 0, 0 );
set_sky_writing_para( SkyWriting, 0, 0, 0 );
set_sky_writing_mode( 3 );
set_sky_writing_limit( 0.5 );

// create and execute list
set_start_list( 1 );
jump_abs( 50000, -50000 );
mark_abs( 50000, 50000 );
mark_abs( -50000, 50000 );
mark_abs( -50000, -50000 );
mark_abs( 50000, -50000 );
jump_abs( 0, 0 );
set_end_of_list();
execute_list( 1 );
}

// END OF SAMPLE SOURCE CODE SNIPPETS.
```

### 3.2.2 Modifying Existing User Programs for excelliSCAN Scan Heads – Basic Steps

To operate an excelliSCAN with the RTC®6, SCANLAB recommends modifying existing user programs as described below. For more details, see the following chapters, as well as the RTC®6 manual. It is assumed that the user's existing program is a complete RTC®6 or RTC®5 application for operating a SCANLAB scan head without SCANAhead technology, for example, an intelliSCAN®.

- (1) After the **load\_correction\_file** command at the beginning of your user program, be sure to insert the command **set\_scanahead\_params** (for parameters, see the command description).  
This activates the RTC®6 board's SCANAhead functionality (incl. laser control!). `Mode = 1` initiates direct querying of the scan head for scan-head-specific information on `PreviewTime`, `Vmax` and `Amax`. Therefore, an excelliSCAN scan head must be connected to the RTC®6 and already and switched-on during user-program runtime.
- (2) Insert **activate\_scanahead\_autodelays**<sup>(1)</sup>.  
This switches on automatic calculation of scanner delays and laser delays.  
All **set\_scanner\_delays** and **set\_laser\_delays** commands in subsequent code lines have no effect, see also notes for **activate\_scanahead\_autodelays**.

- (3) If the original program is an RTC®5 user program, then also make the following changes (for more detailed and comprehensive information, see the RTC®6 manual):

- change `init_rtc5_dll` to `init_rtc6_dll`
- change `rtc5_count_cards` to `rtc6_count_cards`
- change `free_rtc5_dll` to `free_rtc6_dll`
- do NOT<sup>(1)</sup> change `set_rtc5_mode` and `set_rtc4_mode` to `set_rtc6_mode`.

*In practice*, these modifications should already suffice for successful execution of your user program.

Any source code sections for variable polygon delays and sky writing should thereby also be runnable.

Check whether your code is affected by the restrictions mentioned next, in [chapter 3.2.3 "Modifying Existing User Programs for excelliSCAN Scan Heads – Taking Restrictions into Account"](#), page 21.

(1) This section is intended as a quick guide: for detailed information (for example, 3D applications etc.), see the RTC®6 manual.

### 3.2.3 Modifying Existing User Programs for excelliSCAN Scan Heads – Taking Restrictions into Account

While continuing to modify your user program for the excelliSCAN scan head, keep in mind the following:

#### Non-Usable Functionalities of the RTC®6 Board and RTC®6 DLL

- After activation of SCANahead functionality by **set\_scanahead\_params**, the following RTC®6 functionalities are *not* usable (status: DLL ≤601):
  - Processing-on-the-fly
  - Softstart mode
  - Galvanometer-speed-dependent automatic laser control<sup>(1)</sup>
  - Encoder-speed-dependent automatic laser control<sup>(2)</sup>
  - **laser\_on\_pulses\_list**
  - **load\_varpolydelay**

#### Non-Usable iDRIVE® Functionalities

- Unlike with intelliSCAN® scan heads, the following iDRIVE® functions are not available for excelliSCAN scan heads:
  - Switching between tunings  
(**SelectControlDefinition**)  
`control_command (Data = 0x11xx).`
  - Changing the effective calibration  
(**SetPositionScale**)  
`control_command (Data = 0x12xx).`

See [chapter 2.3 "excelliSCAN-Specific Changes of Returned Data with the control\\_command Command"](#), page 14.

(1) Described in RTC®5-Manual [chapter 7.4.9 "Automatic Laser Control"](#), page 156.

(2) Described in RTC®5-Manual [section "Encoder-Speed-Dependent Laser Control"](#) on page 165.

### 3.3 Modifying Existing User Programs – Further Steps, Background Info on SCANahead and excelliSCAN Functions

While continuing to modify your user program for the excelliSCAN scan head, keep in mind the following:

- “Notes on Using Commands for Scanner Delays and Laser Delays”, page 22
- “Notes on Arc Commands”, page 22
- “Notes on Polygon Delays”, page 23
- “Notes on Sky Writing”, page 23
- “Notes on Functions for Automatic Laser Control”, page 24
- “Notes on Controlling Peripherals”, page 24
- “Notes on Unique Characteristics of Returned Data Signals”, page 24
- “Notes on PosAck Status Signal Behavior”, page 24

#### Notes on Using Commands for Scanner Delays and Laser Delays

When using commands with the excelliSCAN to synchronize scan motions and laser control signals, observe the following:

- All relevant SCANahead parameters (article-number-specific) are stored in the excelliSCAN scan head during manufacturing. Although `set_scanahead_params`(Mode = 2,...) allows other values, we recommend only using the values queried from the excelliSCAN scan head. Mode 2 is primarily intended for software development without an attached excelliSCAN scan head.

- For excelliSCAN scan heads, the actual position of the scan motion lags the control values by `PreviewTime`, see [figure 1](#)<sup>(1)</sup>. For synchronous laser control, the laser control signals also need to take `PreviewTime` into account. This can be done manually by appropriately modifying parameters for the `set_scanner_delays` and `set_laser_delays` commands. But here, you must take the excelliSCAN’s speed-dependent acceleration time into account. The preferable alternative is to simply use the `activate_scanahead_autodelays` command for automatic calculation of scanner delays and laser delays. Then, the following applies:
  - The existing command parameters for `set_scanner_delays` and `set_laser_delays` are invalidated by `activate_scanahead_autodelays( Mode = 1 )` and not modified. They become immediately effective again if automatic delay calculation gets deactivated by `activate_scanahead_autodelays( Mode = 0 )`.
  - The command `set_scanahead_params( Mode = 1 or 2, HeadNo, TableNo, PreviewTime, Vmax, Amax )` defines parameters for automatic calculation of scanner delays and laser delays together with `activate_scanahead_autodelays( Mode = 1 )`.
- If needed, throughput of laser-marked workpieces can be increased, if lower quality is acceptable (“process optimization”): see `set_scanahead_line_params( CornerScale, EndScale, AccScale )`. See also [figure 5](#) and [figure 6](#).
- For *fine-tuning* laser delays (for example, to compensate signal propagation times to the laser or to take laser system switching behavior into account), see `set_scanahead_laser_delay_shift( LaserOnDelay, LaserOffDelay )`.

#### Notes on Arc Commands

- excelliSCAN scan heads have a nominal tracking error of 0<sup>(2)</sup>. Tracking-related artifacts (for example, necking during small, quick circular motions) do not occur so long as the maximum

(1) This temporal offset differs quantitatively and qualitatively from tracking error in scan heads without SCANahead technology.

(2) The output delayed by `PreviewTime` is not tracking error in the usual sense.

acceleration of the head is not exceeded (for example, when the source code selects an excessive speed in relation to the circular diameter).

- To estimate maximum acceleration within the image field, you can query the maximum acceleration scaled to an image-field-based bits/10 ms<sup>2</sup> by `get_scanahead_params (HeadNo = 256)`. **Note:** Do not use this queried and rescaled value for `set_scanahead_params (Mode = 2)`.
- To select a suitable speed for a particular circular radius, you can apply the following rule of thumb:  

$$v^2/r < 0.7 \cdot A_{max}^{(1)}$$
 (valid for excelliSCAN 14 with any objective. Insert either control bits or programming bits into the formula). See also [page 22](#).

## Notes on Polygon Delays

- On the excelliSCAN, variable polygon delays work similarly to scan heads without SCANahead technology.  
 To activate variable polygon scanner delays, you still must call the command **set\_delay\_mode** with `VarPoly > 0`.  
 If automatic delay calculation (**activate\_scanahead\_autodelays**) is switched on, its parameters `EdgeLevel`, `MinJumpDelay` and `JumpLengthLimit` have no effect. But they become immediately effective if automatic delay calculation gets switched off.  
 In contrast, the `DirectMove3D` parameter is always effective.
- For excelliSCAN, the **load\_varpolydelay** command has no effect. Currently (status: DLL 601) user-defined variable polygon delay tables are not available.

## Notes on Sky Writing

- For excelliSCAN, sky writing functionality has the same effect as on scan heads without SCANahead technology. All three modes are selectable.  
 To activate sky writing functionality, you must still call the command **set\_sky\_writing** or **set\_sky\_writing\_para** with `Timelag > 1/4 μs`.  
 If automatic delay calculation (**activate\_scanahead\_autodelays**) is switched on, then `Timelag` (except for the actual activation of sky writing) and the parameters `Nprev` and `Npost` have no effect. But they immediately become effective, if automatic delay calculation gets switched off.  
 In contrast, the `LaserOnShift` parameter is always effective.

(1)  $A_{max}$  is queried by `get_scanahead_params (HeadNo = 256)`. Observe the units specified in the command description for **get\_scanahead\_params**.



## Notes on Functions for Automatic Laser Control

- Functions for automatic laser control are currently not usable (status: DLL 601).

## Notes on Controlling Peripherals

When using commands to control peripherals (LASER connector pins ANALOG OUT 1 and ANALOG OUT 2, EXTENSION 1 and EXTENSION 2 headers), observe the following:

If the SCANahead functionality of the RTC<sup>®</sup>6 board has been activated by **set\_scanahead\_params** (PreviewTime > 0), then:

- (1) the control commands **write\_io\_port** and **write\_8bit\_port** are immediately executed (that is, not simultaneously with the galvanometer scanners; "asynchronous").
- (2) execution of the list commands **write\_io\_port\_list** and **write\_write\_8bit\_port\_list** lags by the PreviewTime (that is, simultaneous with the galvanometer scanners; "axissynchronous").

If the SCANahead functionality of the RTC<sup>®</sup>6 board has not been activated (PreviewTime = 0), then asynchronous and axissynchronous execution (1) and (2) are identical; therefore control commands and list commands are handled identically and immediately executed.

With the new laser control mode of the RTC<sup>®</sup>6 (set\_dsp\_mode( 3 )), LASERON delays during a series of short vectors can extend across one or several subsequent vectors. The RTC<sup>®</sup>6 in DSP mode 3 eliminates synthetic scanner delays that prevent this. Output is then synchronous with each vector's corresponding LASERON delay. The list commands **write\_da\_1\_list**, **write\_da\_2\_list**, **write\_da\_x\_list** and the control commands **write\_da\_1**, **write\_da\_2**, **write\_da\_x** are synchronized with the corresponding laser control signals (that is, executed simultaneously with the laser control signals; "lasersynchronous"). With set\_dsp\_mode( 2 ) (RTC<sup>®</sup>5-compatible laser control), axissynchronous and lasersynchronous execution are identical.

## Notes on Unique Characteristics of Returned Data Signals

Some of the excelliSCAN's returned data signals differ from those of other iDRIVE<sup>®</sup> scan heads, for example, intelliSCAN<sup>®</sup>.

### • PosAck Status Value with excelliSCAN

If the threshold is exceeded, then the PosAck bit gets set. It remains set so long as it does not get reset by control\_command (Data = 0x403A).

See chapter 2.2.3 "Returned Data Signal Differences: PosAck Status Signal Behavior after Limit Exceedance", page 10.

### • Position error value with excelliSCAN

control\_command (Data = 0x0503)

This is the difference between the precalculated set position (at 100 clock cycles after the RTC control value) and the actual position (at 120 clock cycles after the control value or 20 clock cycles after the set value) (values apply to excelliSCAN 14).

See chapter 2.2.7 "Timing Diagram of excelliSCAN 14 Scan Head with SCANahead Technology", page 12

## Notes on PosAck Status Signal Behavior

- See chapter 2.2.3 "Returned Data Signal Differences: PosAck Status Signal Behavior after Limit Exceedance", page 10.



### 3.4 RTC®6 Commands - Exclusively for SCANahead Systems

#### Note

- Universally usable RTC®6 commands are described in the RTC®6 manual.

This chapter describes RTC®6 commands intended exclusively for scan heads with SCANahead technology, for example, the excelliSCAN.

This command type is identifiable by the name element “\_scanahead\_”.

All are also available as multi-board commands (status: DLL 601). Multi-board command names begin with the prefix **n\_**.

(n_) <b>activate_scanahead_autodelays</b>	con (1)	...	25
(n_) <b>activate_scanahead_autodelays_list</b>	us (2)		26
(n_) <b>get_scanahead_params</b>	con	.....	26
(n_) <b>set_scanahead_laser_delay_shift</b>	con	.....	28
(n_) <b>set_scanahead_laser_delay_shift_list</b>	us		28
(n_) <b>set_scanahead_line_params</b>	con	.....	29
(n_) <b>set_scanahead_line_params_list</b>	us	.....	29
(n_) <b>set_scanahead_params</b>	con	.....	30

(1) con control command

(2) us undelayed short list command

Ctrl Command	activate_scanahead_autodelays
Function	Switches on or off the automatic (dynamic) calculation of the scanner delays and laser delays. Returns the current mode after the command has been executed.
Call	CurrentMode = activate_scanahead_autodelays ( Mode )
Parameters	<p>Mode Signed 32-bit value.</p> <p>-1: Only returns the current mode. The current mode is not changed.</p> <p>0: Switches off automatic calculation.</p> <p>1: Switches on automatic calculation (Mode = 1) if <b>set_scanahead_params</b> has been called previously. Otherwise, Mode remains 0 after the command has been executed.</p>
Result	Mode as unsigned 32-bit value.
Comments	<ul style="list-style-type: none"> <li>If Mode = 0, then normal scanner delays and laser delays are used (see <b>set_scanner_delays</b> and <b>set_laser_delays</b>). If Mode = 1, then scanner delays and laser delays are calculated and set automatically. Values for Mode = 0 do not get overwritten. After switch-off, they remain available for usage (as with non-excelliSCAN scan heads).</li> <li><b>activate_scanahead_autodelays</b> also affects Sky Writing: the sky writing command parameters Timelag (except for the actual activation of sky writing), Nprev and Npost have no effect. However, they are going to have immediate effect once the automatic delay calculation is switched off. In contrast, the parameter LaserOnShift is always effective.</li> </ul>
RTC®5→ RTC®6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>activate_scanahead_autodelays_list</b> , <b>set_scanner_delays</b> , <b>set_laser_delays</b>

Undelayed Short List Command	<b>activate_scanahead_autodelays_list</b>
Function	Identical with <b>activate_scanahead_autodelays</b> , but an undelayed short list command.
Call	CurrentMode = activate_scanahead_autodelays_list ( Mode )
Parameters	Parameter as unsigned 32-bit value. For values, see <b>activate_scanahead_autodelays</b> .
Comments	<ul style="list-style-type: none"> <li>The <b>activate_scanahead_autodelays_list</b> command takes effect upon the next to-be-calculated delay.</li> <li>Mode = -1 is not available with <b>activate_scanahead_autodelays_list</b>.</li> </ul>
RTC <sup>®</sup> 5→ RTC <sup>®</sup> 6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>activate_scanahead_autodelays</b>

Ctrl Command	<b>get_scanahead_params</b>
Function	Queries certain parameters from the specified scan head. The attached scan head must be an excelliSCAN.
Restriction	The command can be executed only if no list is currently active. Otherwise, the <b>get_last_error</b> return code gets set to RTC6_BUSY and error code 5 is returned.
Call	Error = get_scanahead_params ( HeadNo, &PreviewTime, &Vmax, &Amax )
Parameters	<p>HeadNo      Scan head connector number as unsigned 32-bit value. Allowed values:</p> <p>    = 1: scan head connector 1.</p> <p>    = 2: scan head connector 2 (activation required).</p> <p>    = 256: RTC<sup>®</sup>6 board (no scan head connector). The parameters Vmax and Amax are returned converted to image field coordinates.</p>
Returned parameter values	<p>PreviewTime    Pre-calculation time for galvanometer scanner control in [10 <math>\mu</math>s].</p> <p>Vmax            For HeadNo 1, 2: Velocity limit as control bits (galvanometer scanner rotation angle) [bits/10 <math>\mu</math>s]. For HeadNo 256: Velocity limit as programming bits (image field coordinates) [bits/ms].</p> <p>Amax            For HeadNo 1, 2: Acceleration limit as control bits (galvanometer scanner rotation angle) [bits/10 <math>\mu</math>s<sup>2</sup>]. For HeadNo 256: Acceleration limit as programming bits (image field coordinates) [bits/ms<sup>2</sup>].</p> <p>All values are pointers to unsigned 32-bit values.</p>

Ctrl Command	get_scanahead_params												
Result	<p>Error code as unsigned 32-bit value.</p> <table> <thead> <tr> <th>Value</th><th>Description</th></tr> </thead> <tbody> <tr> <td>3</td><td>No excelliSCAN scan head is attached or its excelliSCAN tuning is not active (<b>get_last_error</b> return code: RTC6_PARAM_ERROR).</td></tr> <tr> <td>5</td><td>A list is currently active (<b>get_last_error</b> return code: RTC6_BUSY).</td></tr> <tr> <td>6</td><td>HeadNo = 0 or HeadNo &gt;2 has been specified as parameter (<b>get_last_error</b> return code: RTC6_PARAM_ERROR).</td></tr> <tr> <td>8</td><td>The RTC<sup>®</sup>6 Board is not responding. Probably a program has not been loaded yet (<b>get_last_error</b> return code: RTC6_TIMEOUT).</td></tr> <tr> <td>11</td><td>A PCI error occurred (<b>get_last_error</b> return code: RTC6_SEND_ERROR).</td></tr> </tbody> </table>	Value	Description	3	No excelliSCAN scan head is attached or its excelliSCAN tuning is not active ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).	5	A list is currently active ( <b>get_last_error</b> return code: RTC6_BUSY).	6	HeadNo = 0 or HeadNo >2 has been specified as parameter ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).	8	The RTC <sup>®</sup> 6 Board is not responding. Probably a program has not been loaded yet ( <b>get_last_error</b> return code: RTC6_TIMEOUT).	11	A PCI error occurred ( <b>get_last_error</b> return code: RTC6_SEND_ERROR).
Value	Description												
3	No excelliSCAN scan head is attached or its excelliSCAN tuning is not active ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).												
5	A list is currently active ( <b>get_last_error</b> return code: RTC6_BUSY).												
6	HeadNo = 0 or HeadNo >2 has been specified as parameter ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).												
8	The RTC <sup>®</sup> 6 Board is not responding. Probably a program has not been loaded yet ( <b>get_last_error</b> return code: RTC6_TIMEOUT).												
11	A PCI error occurred ( <b>get_last_error</b> return code: RTC6_SEND_ERROR).												
Comments	<ul style="list-style-type: none"> <li>The returned parameter values are also used by the <b>set_scanahead_params</b> command.</li> <li><math>V_{max}</math> is the maximum angular velocity of the galvanometers. <math>V_{max}</math> <i>is not</i> the marking speed in the image plane. The returned parameter value unit type is therefore [bits/10 <math>\mu</math>s] and <i>not</i> [bits/ms]. Distortion by the correction file is not yet taken into account in the returned parameter value (see <b>set_scanahead_params</b>).</li> <li>HeadNo = 256 only returns meaningful values if <b>set_scanahead_params</b> was previously called.</li> </ul>												
RTC <sup>®</sup> 5→ RTC <sup>®</sup> 6	New command.												
Version info	Available as of version DLL 600, OUT 600.												
References	<b>set_scanahead_params</b> , <b>get_last_error</b>												

Ctrl Command	<b>set_scanahead_laser_delay_shift</b>
Function	Shifts the LaserOn signals and LaserOff signals temporally forward or back.
Call	set_scanahead_laser_delay_shift ( LaserOnDelay, LaserOffDelay )
Parameters	LaserOnDelay Time shift of LaserOn signals in [0.5 $\mu$ s]. LaserOffDelay Time shift of LaserOff signals in [0.5 $\mu$ s]. Shifts as signed 32-bit values.
Comments	<ul style="list-style-type: none"> <li>The <b>set_scanahead_laser_delay_shift</b> command lets you <i>fine-tune</i> the laser delay, for example, to compensate laser signal propagation times or to take the laser system switching behavior into account.</li> <li>If <b>set_scanahead_params</b> has not been already called and automatic calculation has not been activated (<b>activate_scanahead_autodelays</b> Mode = 0), then the values only get stored, but not applied. But they are applied as soon as required conditions are fulfilled.</li> </ul>
RTC®5→ RTC®6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>set_scanahead_laser_delay_shift_list</b> , <b>set_scanahead_params</b> , <b>activate_scanahead_autodelays</b>

Undelayed Short List Command	<b>set_scanahead_laser_delay_shift_list</b>
Function	Identical with <b>set_scanahead_laser_delay_shift</b> , but an undelayed short list command.
Call	set_scanahead_laser_delay_shift_list ( LaserOnDelay, LaserOffDelay )
Parameters	See <b>set_scanahead_laser_delay_shift</b> .
Comment	<ul style="list-style-type: none"> <li>The <b>set_scanahead_laser_delay_shift_list</b> command takes effect upon the next to-be-calculated delay.</li> </ul>
RTC®5→ RTC®6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>set_scanahead_laser_delay_shift</b>

Ctrl Command	<b>set_scanahead_line_params</b>
Function	Influences the quality of marking results at runtime. Smaller percent values increase throughput at the expense of quality.
Call	set_scanahead_line_params ( CornerScale, EndScale, AccScale )
Parameters	<p>CornerScale      Corner sharpness in percent. 100% = sharp corners.</p> <p>EndScale          Marking accuracy at mark/jump and jump/mark transitions. 100% = straight line ends.</p> <p>AccScale          Determines the portion of the acceleration <i>time</i> (not: distance traversed) in which the laser is active, in percent. 100% = entire acceleration time.</p> <p>Parameters as unsigned 32-bit values.</p>
Comments	<ul style="list-style-type: none"> <li>Only values from 0% to 100% are useful. Higher values do not improve quality (that is, corners cannot be even sharper than sharp), but instead only extend marking times.</li> <li>If <b>set_scanahead_line_params</b> has not been already called, then the values only get stored, but not applied.</li> </ul>
RTC®5→ RTC®6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>set_scanahead_line_params_list</b>

Undelayed Short List Command	<b>set_scanahead_line_params_list</b>
Function	Identical with <b>set_scanahead_line_params</b> , but an undelayed short list command.
Call	set_scanahead_line_params_list ( CornerScale, EndScale, AccScale )
Parameters	See <b>set_scanahead_line_params</b> .
Comment	<ul style="list-style-type: none"> <li>The <b>set_scanahead_line_params_list</b> command takes effect upon the next to-be-calculated delay.</li> </ul>
RTC®5→ RTC®6	New command.
Version info	Available as of version DLL 600, OUT 600.
References	<b>set_scanahead_line_params</b>

Ctrl Command	set_scanahead_params
Function	Activates the RTC <sup>®</sup> 6-SCANahead functionality suitable to control an excelliSCAN scan head. The laser Control and digital inputs/outputs for the peripherals are prepared for an excelliSCAN scan head, that is, delayed by PreviewTime. Thereby scanner delays and laser delays are not automatically calculated. For this purpose serves <b>activate_scanahead_autodelays</b> .
Restriction	The command can only be executed if no list is currently active. Otherwise, the <b>get_last_error</b> return code gets set to RTC6_BUSY and error code 5 is returned.
Call	Error = set_scanahead_params ( Mode, HeadNo, TableNo, PreviewTime, Vmax, Amax )
Parameters	<p>Mode = 0: Deactivates the RTC<sup>®</sup> 6-SCANahead functionality. The additional parameters TableNo, PreviewTime, Vmax, Amax are not taken into account. Mode, for example, for operating intelliSCAN<sup>®</sup> scan heads.</p> <p>= 1: Queries parameters of the scan head with the specified HeadNo and applies them. The parameters PreviewTime, Vmax, Amax are not taken into account. Default mode for operating attached excelliSCANscan heads.</p> <p>= 2: Apply the parameters of this command. Mode, for example, for software development. An excelliSCAN scan head does not need to be connected.</p> <p>HeadNo Number of the scan head connector as unsigned 32-bit value. Allowed values: = 1: scan head connector 1. = 2: scan head connector 2 (activation required).</p> <p>TableNo Allowed range 1–4. A correction file should have been loaded by <b>load_correction_file</b>(..., TableNo, ...). This is used for converting the parameters Amax and Vmax from control bits (galvanometer scanner rotation angle) into programing bits (image field coordinates). See <b>get_scanahead_params</b>.</p> <p>PreviewTime Pre-calculation time for galvanometer scanner control in [10 <math>\mu</math>s]. This parameter is ignored in Mode = 0 and Mode = 1.</p> <p>Vmax Velocity limit as control bits (galvanometer scanner rotation angle) [bits/10 <math>\mu</math>s]. This parameter is ignored in Mode = 0 and Mode = 1.</p> <p>Amax Acceleration limit as control bits (galvanometer scanner rotation angle) [bits/10 <math>\mu</math>s<sup>2</sup>]. This parameter is ignored in Mode = 0 and Mode = 1.</p> <p>All parameters as unsigned 32-bit values.</p>

Ctrl Command	set_scanahead_params														
Result	<p>Error code as unsigned 32-bit value.</p> <table> <tr> <th>Value</th><th>Description</th></tr> <tr> <td>3</td><td>No excelliSCAN scan head attached or excelliSCAN tuning is not active (<b>get_last_error</b> return code: RTC6_PARAM_ERROR).</td></tr> <tr> <td>5</td><td>A list is currently active (<b>get_last_error</b> return code: RTC6_BUSY).</td></tr> <tr> <td>6</td><td>HeadNo = 0 and HeadNo &gt; 2 (<b>get_last_error</b> return code: RTC6_PARAM_ERROR).</td></tr> <tr> <td>7</td><td>The determined scaling factor exceeds 16 or is below 1/16 (possibly no correction file was loaded). The scaling factor is set to 1.</td></tr> <tr> <td>8</td><td>The RTC<sup>®</sup>6 board is not responding. Probably a program has not been loaded yet (<b>get_last_error</b> return code: RTC6_TIMEOUT).</td></tr> <tr> <td>11</td><td>A PCI error occurred (<b>get_last_error</b> return code: RTC6_SEND_ERROR)</td></tr> </table>	Value	Description	3	No excelliSCAN scan head attached or excelliSCAN tuning is not active ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).	5	A list is currently active ( <b>get_last_error</b> return code: RTC6_BUSY).	6	HeadNo = 0 and HeadNo > 2 ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).	7	The determined scaling factor exceeds 16 or is below 1/16 (possibly no correction file was loaded). The scaling factor is set to 1.	8	The RTC <sup>®</sup> 6 board is not responding. Probably a program has not been loaded yet ( <b>get_last_error</b> return code: RTC6_TIMEOUT).	11	A PCI error occurred ( <b>get_last_error</b> return code: RTC6_SEND_ERROR)
Value	Description														
3	No excelliSCAN scan head attached or excelliSCAN tuning is not active ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).														
5	A list is currently active ( <b>get_last_error</b> return code: RTC6_BUSY).														
6	HeadNo = 0 and HeadNo > 2 ( <b>get_last_error</b> return code: RTC6_PARAM_ERROR).														
7	The determined scaling factor exceeds 16 or is below 1/16 (possibly no correction file was loaded). The scaling factor is set to 1.														
8	The RTC <sup>®</sup> 6 board is not responding. Probably a program has not been loaded yet ( <b>get_last_error</b> return code: RTC6_TIMEOUT).														
11	A PCI error occurred ( <b>get_last_error</b> return code: RTC6_SEND_ERROR)														
Comments	<ul style="list-style-type: none"> <li>The V<sub>max</sub> and A<sub>max</sub> parameters are used for automatic calculation of scanner delays and laser delays, see <b>activate_scanahead_autodelays</b>.</li> <li>The values for V<sub>max</sub> and A<sub>max</sub> are specified as control bits (galvanometer scanner rotation angles). Information is read-out from the correction file and used for an internal conversion into programing bits (sample values). Therefore, the correction file needs to be specified in the TableNo parameter. At conversion time, the correction file must already be loaded on the board, but does not yet need to be assigned. The system cannot reliably detect correction files that have not been loaded. The V<sub>max</sub> and A<sub>max</sub> values which have been converted into programing bits can be queried by <b>get_scanahead_params</b>(HeadNo = 256).</li> <li>For error return information, see <b>get_scanahead_params</b>.</li> <li>Mode = 1 results in aborted command execution (Error = 3) if no excelliSCAN is attached and active. All SCANahead functionality is deactivated. Parameters specified for Mode = 2 are not applied!</li> <li>The <b>set_scanahead_params</b> command waits until the last session has finished traversing, that is, the HEAD_BUSY signal (bit #23) from <b>get_status</b> is no longer set. In any case, it waits no longer than 255 × [10 μs].</li> </ul>														
RTC <sup>®</sup> 5 → RTC <sup>®</sup> 6	New command.														
Version info	Available as of version DLL 600, OUT 600.														
References	<b>get_scanahead_params</b> , <b>activate_scanahead_autodelays</b> , <b>get_last_error</b> , <b>get_status</b> , <b>load_correction_file</b>														



## Notes